


Expressive Motion Capture TOOLBOX

SCHEMA TOOLBOX



PROJECTS

ALLIAGE

single

group



Kinetic energy, entropy, acceleration

Demo_1Alliage_Single.m

Demo_1Alliage_Group.m

Group Convergence

EMODANCE



Demo_2Emodance.m

MOCO V3



Kinetic energy, angles

Demo_3MocoV3.m

IMPROV

- (Not yet ready with the new toolbox)

ORCHESTRA

- (Not yet ready with the new toolbox)

JPO

Different types of analysis

Demo_4JPO.m

numberplot, deplacementhistogram, nbroomhistogram, durationparhistogram, durationroomhistogram

```

%% PATH
pathComputer = '/Users';

%% TOOLBOX
% Add path for toolbox
addpath(genpath([pathComputer, filesep, '0434_EMC_Toolbox']))

%% LOAD
% Load a file - 1 Body
cfg = []; % Empty cfg
cfg.fillGapFlag = true;
cfg.removePrefix = {'S01_'};
cfg.absolutePositionFlag = true;
cfg.headMarkers = {'LFHD', 'RFHD', 'OZ'};
% Classification
cfg.classificationFlag = true;
cfg.classificationType = 'prefix';
cfg.classInfo = {'whole_anticipation', 'piano_forte'};
cfg.classPrefixPosition = {1,3}; % Give the range where the prefix is
positioned within the filename
cfg.classListPrefix = {'w', 'a'}, ...
    {'p', 'f'}; % List of possible prefixes
cfg.classListValue = {{1,2}, ...
    {1,2}}; % Categorisation number
tsvFile1 = emcLoad([pathComputer, filesep, 'example1.tsv'], cfg);
tsvFile2 = emcLoad([pathComputer, filesep, 'example2.tsv'], cfg);

%% PLOT
% Body
cfg.connectionMatrix = [1 2; 2 3; 1 3; 3 4; 4 5; 4 6; 4 13; 5 7; 7 9; 6 8; 8 10; 11 12; 4 14];
emcPlotBody(tsvFile1, cfg)
emcPlotBody(tsvFile2, cfg)
% Quiver
cfg.plotBodyFlag = true;
emcPlotQuiver(tsvFile1, cfg)
emcPlotQuiver(tsvFile2, cfg)

% Markers
cfg.plotMarkerList = {'LWRB', 'RWRB'};
emcPlotMarker(tsvFile1, cfg)
% Compare
cfg.plotMarkerList = {'RWRB'};
emcPlotCompare(tsvFile1, tsvFile2, cfg)

%% PREPROCESSING
cfg.preprocessing.preprocessingType = {'center', 'rotation frontal'};
cfg.preprocessing.markerFrontalList = {'LSHO', 'RSHO'};
tsvFile1 = emcPreprocessing(tsvFile1, cfg.preprocessing);
tsvFile2 = emcPreprocessing(tsvFile2, cfg.preprocessing);
% Plot to see the difference
emcPlotBody(tsvFile1, cfg)

```

```
%% PROCESSING
% Display
cfg.display = true;
% Speed
cfg.deriv = 1;
cfg.euclidianFlag = true;
tsvFile1 = emcDerivative(tsvFile1,cfg);
tsvFile2 = emcDerivative(tsvFile2,cfg);
% Convexhull
tsvFile1 = emcConvexhull(tsvFile1,cfg);
tsvFile2 = emcConvexhull(tsvFile2,cfg);
% Synchronisation
cfg.syncType = 'intra';
cfg.dataType = 'marker';
cfg.dataList = {'LELB';'RELB';'LWRB';'RWRB'};
[ syncQ, syncq ] = emcEventSync( tsvFile1, cfg );
[ syncQ, syncq ] = emcEventSync( tsvFile2, cfg );

%% MORE PLOT
cfg.step = 30;
cfg.width = 400;
cfg.visSeqFeature = 'speed';
emcVisualSequence(tsvFile1, cfg)

%% SAVE
emcSaveGraph([pathComputer, filesep, 'Output'])
```

FORMAT

emcConvertC3D2TSV

description

Opens a C3D file and convert it into a TSV file. TSV file is saved afterwards

syntax

```
emcConvertC3D2TSV( filename, cfg );
```

input parameters

filename: string containing the path or filename of the file to convert

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.outputDir: string containing the path to the output directory

*.deleteMarker: cell array of markers names to be deleted

*.changeMarker: cell array of markers names to be changed

*.orderMarker: cell array containing the final order of the list of markers names

*.fillgapFlag: boolean indicating if use fillgap or not (from Motion Capture Toolbox)

output

[]

Examples

```
cfg.outputDir = 'C:\Users\Desktop';
```

```
cfg.deleteMarker = {'d'};
```

```
cfg.changeMarker = {'tutu','e'; 'baba','f'};
```

```
cfg.orderMarker = {'a','b','e','f','c'};
```

```
cfg.fillgapFlag = true;
```

```
emcConvertC3D2TSV( 'motion.c3d', cfg );
```

comments

-

see also

-

FORMAT

emcDivideMultipleBodies

description

Divides a TSV file containing multiple bodies (represented by prefixe) into multiple files containing one body and save them

syntax

emcDivideMultipleBodies(filename, cfg)

input parameters

filename: string containing the path or filename of the file to convert

cfg: configuration structure

[MANDATORY]

*.prefixBodyList: cell array of prefix name for every body

[OPTIONAL]

*.outputDir: string containing the path to the output directory

output

[]

Examples

```
cfg.prefixBodyList = {'body1_', 'body2_'};
```

```
cfg.outputDir = 'C:\Users\Desktop';
```

```
emcDivideMultipleBodies('motion.c3d', cfg);
```

comments

Saves the different file as "filename_prefixBody.tsv"

see also

-

FORMAT

emcMidpointBaricenter

description

Computes the baricenter of a list of multiple markers and the middle point between the first two markers of the list. The baricenter and middle point are added to the marker list in the tsvFile

syntax

```
tsvFile = emcMidpointBaricenter(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.transformMarker: cell array of markernames on which the baricenter and the midpoint will be computed

*.transformName: string containing the name of the group of markers creating the baricenter and middle point

[OPTIONAL]

-

output

tsvFile: MoCap data structure

Examples

```
cfg.transformMarker = {'a','b','c'};
```

```
cfg.transformName = {'abc'};
```

```
tsvFile = emcMidpointBaricenter(tsvFile, cfg);
```

comments

The markers created are a combination of the transformName and either "Bar" for Baricenter or "Mid" for Middle point

see also

emcVerticalLine

FORMAT

emcOrderMarker

description

Reorders tsvFile placing markers into a specific order

syntax

```
tsvFileOrdered = emcOrderMarker( tsvFile, cfg );
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.orderMarker: cell array of markernames in the specific order

[OPTIONAL]

-

output

tsvFileOrder: MoCap data structure (with marker in a different order)

examples

```
cfg.orderMarker = {'b','a','c'};
```

```
tsvFile = emcOrderMarker( tsvFile, cfg );
```

comments

-

see also

-

FORMAT

emcVerticalLine

description

Creates a second marker right above a specific marker in order to draw a vertical line between them

syntax

```
tsvFile = emcVerticalLine( tsvFile, cfg );
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.transformMarker: cell array or string containing markername(s)

[OPTIONAL]

-

output

tsvFile: MoCap data structure

examples

```
cfg.transformMarker = {'a'};
```

```
tsvFile = emcMidpointBaricenter(tsvFile, cfg);
```

comments

The markers created are a combination of the markername and "Vert" for Vertical line.

This can be further use to compare angle to a straight line or to have an idea of how bended the movement is compared to a straight vertical line

see also

emcMidpointBaricenter

FORMAT

emcAlignHeightMarkerBaricenter

description

Aligns markers to the height of the baricenter of a collection of markers.

syntax

```
tsvFile = emcAlignHeightMarkerBaricenter(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.transformMarker: string containing the path to the output directory

*.alignMarker: cell array of markers names to be deleted

[OPTIONAL]

-

output

[]

examples

```
cfg.transformMarker = {'a','b'};
```

```
cfg.alignMarker = {'c'};
```

```
tsvFile = emcAlignHeightMarkerBaricenter(tsvFile, cfg);
```

comments

-

see also

-

LOAD

emcLoadSingle

description

Loads a single tsv file from the filename into a structure

syntax

```
tsvFile = emcLoadSingle(filename, cfg);
```

input parameters

filename: string containing the path or filename of the file to load

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.makersToKeep: cell array containing the markers names to be kept in the tsv structure

*.fillgapFlag: boolean indicating if use fillgap or not (from Motion Capture Toolbox)

*.classificationFlag: boolean indicating if emcClassification should be run

*.absolutePositionFlag: boolean indicating if emcAbsolutePosition should be run

*.removePrefixFlag: boolean indicating if emcRemovePrefix should be run

output

tsvFile: MoCap data structure

examples

```
tsvFile1 = emcLoadSingle('motion1.tsv', cfg);
```

```
cfg.makersToKeep = {'a','b','c'};
```

```
cfg.fillgapFlag = true;
```

```
cfg.absolutePositionFlag = true;
```

```
cfg.removePrefixFlag = true;
```

```
cfg.removePrefix = {'body1_'};
```

```
cfg.classificationFlag = true;
```

```
cfg.classificationType = 'prefix';
```

```
cfg.classInfo = {'className1','className2'};
```

```
cfg.classPrefixPosition = {1,2};
```

```
cfg.classListPrefix = {'1','2','3'},...
```

```
    {'1','2'};
```

```
cfg.classListValue = {'class1_1','class1_2','class1_3'},...
```

```
    {'class1_2','class2_2'};
```

```
tsvFile2 = emcLoadSingle('motion2.tsv', cfg);
```

comments

-

see also

emcClassification

emcAbsolutePosition

emcRemovePrefixFlag

LOAD

emcClassification

description

Adds tags to the tsv structure for classification. This can be made according to different methods: "prefix", uses the filename given and extract information at specific location

syntax

```
tsvFile = emcClassification(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

- *.classificationType: define the classification method

if cfg.classificationType: 'prefix'

- *.classInfo: cell array containing the classes name

- *.classPrefixPosition: cell array containing the indexes of the classification letters in the filename

- *.classListPrefix: cell array containing the different options available at the position mentionned in cfg.classPrefixPosition

- *.classListValue: cell array containing the value of each of the options available in cfg.classListPrefix

[OPTIONAL]

-

output

tsvFile: MoCap data structure

examples

```
cfg.classificationType = 'prefix';
```

```
cfg.classInfo = {'className1','className2'};
```

```
cfg.classPrefixPosition = {1,2};
```

```
cfg.classListPrefix = {'1','2','3'},...
```

```
    {'1','2'};
```

```
cfg.classListValue = {'class1_1','class1_2','class1_3'},...
```

```
    {'class1_2','class2_2'};
```

```
tsvFile = emcClassification(tsvFile, cfg);
```

comments

if store the classification in tsvFile.info.classification

see also

emcLoadSingle

LOAD

emcAbsolutePosition

description

Store the absolute position of tsvFile (timecourse of the first marker).
Useful if need to be modify with for example preprocessing steps such as mccenter.

syntax

```
tsvFile = emcAbsolutePosition(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.headMarkers: cell array with markers of the head

output

tsvFile: MoCap data structure

examples

```
cfg.headMarkers = {'head1','head2'};
```

```
tsvFile = emcAbsolutePosition(tsvFile, cfg);
```

comments

Stores the absolute postion in tsvFile.info.absolutePosition

see also

emcLoadSingle

LOAD

emcRemovePrefix

description

Removes a prefix / different prefixes to the list of markers of a tsvFile

syntax

```
tsvFile = emcRemovePrefix(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.removePrefix: string or cell array containing the prefix

[OPTIONAL]

-

output

tsvFile: MoCap data structure

examples

```
cfg.removePrefix = {'body1_'};
```

```
tsvFile = emcRemovePrefix(tsvFile, cfg);
```

comments

stores the prefix in tsvFile.info.removePrefix

see also

emcLoadSingle

PREPROCESSING

emcPreprocessing

description

Preprocessing of a tsvFile. Includes methods such as mc2frontal, mcrotate, mccenter, mccenter_marker, mcnorm, and mcsmoother from the Motion Capture Toolbox, Copyright 2008, University of Jyväskylä, Finland

syntax

```
tsvFile = emcPreprocessing(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

- *.preprocessingType: cell array with the type(s) of preprocessing method to be applied

- if cfg.preprocessingType: 'rotation frontal'

- *.markerFrontalList: list with the markers index defining the frontal plane (see mc2frontal)

- if cfg.preprocessingType: 'rotation'

- *.rotationAngleValue: value of the rotation (see mcrotate)

- *.rotationAngleAxis: list defining the axis (see mcrotate)

- if cfg.preprocessingType: 'center marker'

- *.markerToCenter: string marker name of the marker on which the rest of the data is centered

- if cfg.preprocessingType: 'smoother'

- *.smoothValue: int smooth value (see mcsmoother)

[OPTIONAL]

-

output

tsvFile: MoCap data structure

examples

```
cfg.preprocessingType = {'rotation frontal', 'rotation', 'center', 'center marker', 'normalize',  
'smoother'};  
cfg.markerFrontalList = [1 2];  
cfg.rotationAngleValue = 30;  
cfg.rotationAngleAxis = [1 0 0];  
cfg.markerToCenter = 'head';  
cfg.smoothValue = 20;  
tsvFile = emcPreprocessing(tsvFile, cfg);
```

comments

see also

mc2frontal

mcrotate

mccenter

mccenter_marker

mcnorm

mcsmoother

PROCESSING

emcConvexhull

description

Computes the convexhull

syntax

```
tsvFile = emcConvexhull(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.frame: int value of the frame at which the body should be displayed

*.display: boolean deciding if a figure is to be plotted (default: true)

if cfg.display: true

*.connectionMatrix: [mandatory] list of indexes defining the connection of the body (see emcPlotBody3D)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.frame = 40;
```

```
cfg.display = true
```

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
tsvFile = emcConvexhull(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.convexhull

see also

-

PROCESSING

emcCumulativeDistance

description

Computes the cumulative distance

syntax

```
tsvFile = emcCumulativeDistance(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcCumulativeDistance(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.cumuldist

see also

-

PROCESSING

emcDensity

description

Computes the density - the average distance of all markers from the baricenter

syntax

```
tsvFile = emcDensity(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcDensity(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.density

see also

-

PROCESSING

emcDerivative

description

Computes the derivative of the motion

syntax

```
tsvFile = emcDerivative(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.deriv: int order of the derivative to be calculated - 1 (speed), 2 (acceleration), 3 (jerk)

*.euclidianFlag: boolean to determine if the script uses euclidian norm after derivative

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcDerivative(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.speed

feature is saved in tsvFile.processing.acceleration

feature is saved in tsvFile.processing.jerk

see also

-

PROCESSING

emcDirectness

description

Computes the directness - Movement Directness Index is computed from a trajectory drawn in the space by a joint as the ratio between the euclidean distance, calculated between the starting and the ending point of the trajectory, and the trajectory's actual length. [Piana, 2013]

syntax

```
tsvFile = emcDirectness(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcDirectness(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.directness

see also

-

PROCESSING

emcDistance

description

Computes the distance between 2 markers or to the ground from one marker

syntax

```
tsvFile = emcDistance(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.featDistMarker: cell array containing 2 markernames or 1 markernames and "ground"

[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featDistMarker = {'a','b'};
```

```
cfg.display = true
```

```
tsvFile = emcDistance(tsvFile, cfg);
```

```
cfg.featDistMarker = {'a','ground'};
```

```
cfg.display = true
```

```
tsvFile = emcDistance(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.distance

see also

-

PROCESSING

emcEventSync

description

Computes the synchronicity matrix for different markers, bodies or features as defined by Albordo, 2016

syntax

```
tsvFile = emcEventSync(tsvFile1[, tsvFile2], cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.syncType: str type of synchrony - 'intra' (for one body, compares inside one body), 'inter' (for multiple body, compares bodies one against the other)

*.dataType: str type of data - 'marker' (on the marker motion), 'feature' (on the computed features)

[OPTIONAL]

*.dataList: cell array containing the markernames or feature names on which the sync is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

syncQ: table overall degree of sync

syncq: table overall degree of delay

examples

```
cfg.syncType = 'intra';
```

```
cfg.dataType = 'marker';
```

```
cfg.dataList = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcEventSync(tsvFile, cfg);
```

```
cfg.syncType = 'inter';
```

```
cfg.dataType = 'feature';
```

```
cfg.dataList = {'speed', 'convexhull'};
```

```
cfg.display = true
```

```
tsvFile = emcEventSync(tsvFile1, tsvFile2, cfg);
```

comments

feature is saved in tsvFile.processing.directness

see also

-

PROCESSING

emcFluidity

description

Computes the fluidity

The principle of the curvature can be applied to the movement velocity and its variation in time to calculate the movement fluidity (FI): high curvature of the speed trajectory in time means low fluidity, while low curvature means high fluidity. To calculate the fluidity we compute the curvature of the tangential velocity of the desired joint. [Piana, 2013]

syntax

```
tsvFile = emcFluidity(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.featMarker: cell array containing the marker names on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcFluidity(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.fluidity

see also

-

PROCESSING

emcHandsSpeed

description

Computes the speed of the hands

syntax

```
tsvFile = emcHandsSpeed(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.handsMarkers: cell array containing the markernames for the hands

*.euclidianFlag: boolean to determine if the script uses euclidian

norm after derivative

[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.handsMarkers = {'a','b'};
```

```
cfg.display = true
```

```
cfg.euclidianFlag = true;
```

```
tsvFile = emcHandsSpeed(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.speed

see also

-

PROCESSING

emcSymmetry

description

Computes the symmetry between the left and right part of the body as defined by Piana 2013

syntax

```
tsvFile = emcSymmetry(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.leftPrefix: string prefix of the left side of the body markernames

-- they should all start with this prefix

*.rightPrefix: string prefix of the right side of the body markernames

-- they should all start with this prefix

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.leftPrefix = 'L';
```

```
cfg.rightPrefix = 'R';
```

```
cfg.featMarker = {'Ra','Rb','Lc','Ld'};
```

```
cfg.display = true
```

```
tsvFile = emcSymmetry(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.symmetry

see also

-

PROCESSING

emcUpwardMovement

description

Computes the amount of upward movement, everytime a marker is going up on the Z axis, the value for the feature increases

syntax

```
tsvFile = emcUpwardMovement(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.featMarker: cell array containing the markernames on which the feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featMarker = {'a','b','c'};
```

```
cfg.display = true
```

```
tsvFile = emcUpwardMovement(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.upwardMovement

see also

-

PROCESSING

emcHeatmap

description

Computes the heatmap of the baricenter motion seen only on a 2D plane (x-y) from above.

syntax

```
tsvFile = emcHeatmap(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.heatmapFeature: str feature name to modulate the value of the heatmap

output

-

examples

```
cfg.heatmapFeature = 'speed';
```

```
cfg.reduceFlag = true;
```

```
cfg.reduceResolution = [2,3];
```

```
emcHeatmap(tsvFile, cfg);
```

comments

-

see also

emcHeatmapData

PROCESSING

emcHeatmapData

description

Computes the heatmap of the baricenter motion seen only on a 2D plane (x-y) from above.

syntax

```
tsvFile = emcHeatmap(dataMotion[, dataFeature], cfg)
```

input parameters

dataMotion: table motion data (3 columns per marker, each line represent the position of the marker at time t)

dataFeature: table feature data

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.reduceFlag: boolean flag meaning that the final resolution will be reduced

if reduceFlag: true

*.reduceResolution: [mandatory] table with 2 values - the reduction factor for X and Y.

output

-

examples

```
cfg.reduceFlag = true;
```

```
cfg.reduceResolution = [2,3];
```

```
emcHeatmapData(motionData, featureData, cfg);
```

comments

-

see also

emcHeatmap

PROCESSING

emcGroupConvergence

description

Computes convergence of lines of sight. Either globally between a fixed point and the intersection of all lines for sight or partially between the different bodies

syntax

```
tsvFile = emcGroupConvergence(tsvFile,tsvFile2[, tsvFile3,...], cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.convergenceType: str type of convergence - global: calculating the distance between the intersection of all line of sight and a fixed point. Partial: calculating the distance between one body and the line of sight converging of all the other bodies

*.headMarker: cell array containing the markernames for the head defining the line of sight (suggestion: use baricenter and middlepoint)
[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

*.displayVerification: boolean deciding if a figure is to be plotted for verification of the line of sights(default: false)

output

tsvFile: MoCap data structure

examples

```
cfg.convergenceType = 'global';
```

```
cfg.headMarker = {'HEADBar','HEADMid'}
```

```
tsvFile = emcGroupConvergence(tsvFile,tsvFile2, tsvFile3, cfg));
```

comments

feature is saved in tsvFile.processing.groupConvGlobal/tsvFile.processing.groupConvPartial

see also

-

PROCESSING

emcAngleVector

description

Computes the angle between 2 lines, each of which is defined by 2 markers

syntax

```
tsvFile = emcAngleVector(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.angleName: str name of the angle

*.angleVector: cell array defining the 2 lines (4 markers)

[OPTIONAL]

*.angleDim: int value representing the dimension in which the angle is calculated – if 2: angle is computed only in the X-Y space. if 3:

angle is computed in the X-Y-Z space (default: 3)

feature is calculated (default: all)

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.angleName = 'bending';
```

```
cfg.angleVector = {'a','b'},{'c','d'};
```

```
cfg.angleDim = 3;
```

```
cfg.display = true;
```

```
tsvFile = emcAngleVector(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.(angleName)

see also

-

PROCESSING

emcKineticEnergy

description

Computes the kinetic energy of the markers (based on mcpotenergy from the Motion Capture Toolbox, Copyright 2008, University of Jyväskylä, Finland)

syntax

tsvFile = emcKineticEnergy(tsvFile, cfg)

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.m2jpar: vector contraining the index of the markers for the transformation to joints (see the Motion Capture Toolbox)

*.j2spar: vector contraining the index of the joints for the transformation to segments (see the Motion Capture Toolbox)

*.mcspar: vector contraining the weights of all the segments (see the Motion Capture Toolbox)

*.paramComputation: str flag defining the mean of concatenation of the data - 'mean', 'sum', 'median'

[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.m2jpar.type = 'm2jpar';
cfg.m2jpar.nMarkers = 22;
cfg.m2jpar.markerNum = {[4,9,11,12],[4,11],[4,5,1],[1,2,3]};
cfg.m2jpar.markerName = {'PELVIS', 'RPELV', 'RTHIGH', 'RTIB'};
cfg.j2spar.type = 'j2spar';
cfg.j2spar.rootMarker = 1;
cfg.j2spar.frontalPlane = [1 2];
cfg.j2spar.parent = [0 1 2 3];
cfg.j2spar.segmentName = cfg.m2jpar.markerName;
cfg.segmidx = [0 1 8 7];
cfg.mcspar = mcgetsegmpar('Dempster', cfg.segmidx);
cfg.paramComputation = 'mean';
cfg.display = true;
tsvFile = emcKineticEnergy(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.kinEnergy

see also

mckinenergy

PROCESSING

emcPotentialEnergy

description

Computes the potential energy of the markers (based on mcpotenergy from the Motion Capture Toolbox, Copyright 2008, University of Jyväskylä, Finland)

syntax

tsvFile = emcPotentialEnergy(tsvFile, cfg)

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.m2jpar: vector contraining the index of the markers for the transformation to joints (see the Motion Capture Toolbox)

*.j2spar: vector contraining the index of the joints for the transformation to segments (see the Motion Capture Toolbox)

*.mcspar: vector contraining the weights of all the segments (see the Motion Capture Toolbox)

*.paramComputation: str flag defining the mean of concatenation of the data - 'mean', 'sum', 'median'

[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.m2jpar.type = 'm2jpar';
cfg.m2jpar.nMarkers = 22;
cfg.m2jpar.markerNum = {[4,9,11,12],[4,11],[4,5,1],[1,2,3]};
cfg.m2jpar.markerName = {'PELVIS', 'RPELV', 'RTHIGH', 'RTIB'};
cfg.j2spar.type = 'j2spar';
cfg.j2spar.rootMarker = 1;
cfg.j2spar.frontalPlane = [1 2];
cfg.j2spar.parent = [0 1 2 3];
cfg.j2spar.segmentName = cfg.m2jpar.markerName;
cfg.segmidx = [0 1 8 7];
cfg.mcspar = mcgetsegmpar('Dempster', cfg.segmidx);
cfg.paramComputation = 'mean';
cfg.display = true;
tsvFile = emcPotentialEnergy(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.potEnerg

see also

mcpotenergy

PROCESSING

emcPositionHands

description

Computes the amount of time the hands spend in either the upper, middle or lower part of the body. The upper part corresponds to "above the head", the middle corresponds to "between the head and pelvis", lower part corresponds to "below the pelvis"

syntax

```
tsvFile = emcPositionHands(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.headMarker: cell array containing one markername for the head

*.pelvisMarker: cell array containing one markername for the pelvis

*.handsMarker: cell array containing two markername for the two hands

[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.headMarker = {'a'};
```

```
cfg.pelvisMarker = {'a'};
```

```
cfg.handsMarker = {'c','d'};
```

```
cfg.display = true;
```

```
tsvFile = emcPositionHands(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.positionHands

see also

-

PROCESSING

emcSampleEntropy

description

Computes the sample entropy of a feature

syntax

```
tsvFile = emcSampleEntropy(tsvFile, cfg)
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.featureName: str feature name on which the sample entropy will be computed

[OPTIONAL]

*.display: boolean deciding if a figure is to be plotted (default: true)

output

tsvFile: MoCap data structure

examples

```
cfg.featureName = 'kinEnerg';
```

```
cfg.display = true;
```

```
tsvFile = emcSampleEntropy(tsvFile, cfg);
```

comments

feature is saved in tsvFile.processing.entrop

see also

-

PLOT

emcPlotCompare

description

Plots the motion capture data of markers selected on the three axes X, Y, and Z. Can take as many tsvfile as wanted and plot them in different colors to compare them.

syntax

```
emcPlotCompare(tsvFile1[, tsvFile2,...], cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.plotMarkerList: cell array with markers to be plotted (if not defined all markers will be used)

output

-

examples

```
cfg.plotMarkerList = {'a','b','c'};
```

```
emcPlotCompare(tsvFile1, tsvFile2, cfg);
```

comments

-

see also

-

PLOT

emcPlotMarker

description

Plots the motion capture data of different markers selected in cfg in different colours on the three axis X, Y, and Z

syntax

```
emcPlotMarker(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.plotMarkerList: cell array with markers to be plotted (if not defined all markers will be used)

output

-

examples

```
cfg.plotMarkerList = {'a','b','c'};
```

```
emcPlotMarker(tsvFile, cfg);
```

comments

-

see also

-

PLOT

emcPlotQuiver

description

Plots markers, their line of movement in space as well as arrows for Speed and acceleration using the function Quiver from Matlab

syntax

```
emcPlotQuiver(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.step: int value defining the step between two arrows (default: 20)

*.plotMarkerList: cell array with markers to be plotted (if not defined all markers will be used)

*.plotBodyFlag: boolean flag defining if the body structure is printed or not

if cfg.plotBodyFlag: true

*.connectionMatrix: list of indexes defining the connection of the body (see emcPlotBody3D)

output

-

examples

```
cfg.step = 40;
```

```
cfg.plotMarkerList = {'a','b','c'};
```

```
cfg.plotBodyFlag = true;
```

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
emcPlotQuiver(tsvFile, cfg);
```

comments

-

see also

emcPlotBody3D

PLOT

emcPlotBody3D

description

Plots the structure of the body in 3D

syntax

```
emcPlotBody3D(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.connectionMatrix: list of indexes defining the connection of the body (see emcPlotBody3D)

[OPTIONAL]

*.frame: int value defining the frame at which the marker should be printed (default: random)

*.lineVector: cell array containing pairs of markers defining red lines

output

-

examples

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
cfg.frame = 40;
```

```
cfg.lineVector = {'a','b'},{'b','c'};
```

```
emcPlotBody3D(tsvFile, cfg);
```

comments

-

see also

-

PLOT

emcAnimation

description

Creates an animation of the motion capture data with the function `mcanimate` from the Motion Capture Toolbox, Copyright 2008, University of Jyväskylä, Finland

syntax

```
emcAnimation(tsvFile, cfg);
```

input parameters

`tsvFile`: MoCap data structure

`cfg`: configuration structure

[MANDATORY]

- *.`connectionMatrix`: list of indexes defining the connection of the body (see `emcPlotBody3D`)

- *.`dataMapar`: str path pointing at `mcdemodata.mat` from the Motion Capture Toolbox, Copyright 2008, University of Jyväskylä, Finland

[OPTIONAL]

- *.`fps`: int number of frame per second at which the points will be displayed in the animation (default: 30)

- *.`msize`: int size at which the points will be displayed (default: 2)
lines

output

-

examples

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
cfg.dataMapar = 'C:/test/mcdemodata.mat';
```

```
cfg.fps = 40;
```

```
cfg.msize = 3;
```

```
emcAnimation(tsvFile, cfg);
```

comments

-

see also

`mcanimate`

PLOT

emcVideoFeature

description

Plots an animation of both the body moving and a defined feature evolving over time

syntax

```
emcVideoFeature(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.connectionMatrix: list of indexes defining the connection of the body (see emcPlotBody3D)

*.videoFeature: str feature name to be displayed

[OPTIONAL]

*.step: int number of frames to skip in between two timestamps (default: 50)

*.videoName: str name of the video to be saved

*.videoFrameRate: int framerate at which the video is recorded

output

-

examples

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
cfg.videoFeature = 'speed';
```

```
cfg.step = 30;
```

```
cfg.videoName = 'testVideo.avi';
```

```
cfg.videoFrameRate = 45;
```

```
emcVideoFeature(tsvFile, cfg);
```

comments

Feature must have been computed beforehand using funciton in Processing Directory

see also

-

PLOT

emcVideoFeatureGroup

description

Plots an animation of both the bodies of a group of people moving and a defined feature evolving over time

syntax

```
emcVideoFeatureGroup(tsvFile1, tsvFile2, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

*.connectionMatrix: list of indexes defining the connection of the body (see emcPlotBody3D)

*.videoFeature: str feature name to be displayed

[OPTIONAL]

*.step: int number of frames to skip in between two timestamps (default: 50)

*.videoName: str name of the video to be saved

*.videoFrameRate: int framerate at which the video is recorded

output

-

examples

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
cfg.videoFeature = 'speed';
```

```
cfg.step = 30;
```

```
cfg.videoName = 'testVideo.avi';
```

```
cfg.videoFrameRate = 45;
```

```
emcVideoFeature(tsvFile1, tsvFile2, cfg);
```

comments

Feature must have been computed beforehand using funciton in Processing Directory

see also

-

PLOT

emcVisualSequence

description

Plots a sequence of the full movement frame after frame in one image (chronophotographic) and a boxed representation of the magnitude of the defined feature

syntax

```
emcVisualSequence(tsvFile, cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

- *.connectionMatrix: list of indexes defining the connection of the body (see emcPlotBody3D)

- *.visSeqFeature: str feature name to be displayed

[OPTIONAL]

- *.step: int number of frames to skip in between two timestamps (default: 50)

- *.width: str width of a single frame within the chronophotographic (default: 40)

output

-

examples

```
cfg.connectionMatrix = [1 2; 2 3; 1 3]
```

```
cfg.visSeqFeature = 'speed';
```

```
cfg.step = 30;
```

```
cfg.width = 50;
```

```
emcVisualSequence(tsvFile, cfg);
```

comments

-

see also

-

SAVE

emcSaveGraph

Description

Saves all the graphs opened and active

syntax

```
emcSaveGraph(outputDir);
```

input parameters

outputDir: str path where to save all graphs

output

-

examples

```
emcSaveGraph('C:/save');
```

comments

Saves every graph using the name given when opening the feature.

Saves graph in pdf format

see also

-

SAVE

emcSaveFeature

Description

Save feature into csv files format (one feature per file) & a summary file

syntax

```
emcSaveFeature(tsvFile1[, tsvFile2,...], cfg);
```

input parameters

tsvFile: MoCap data structure

cfg: configuration structure

[MANDATORY]

-

[OPTIONAL]

*.saveSingleFeatureFlag: boolean flag defining is single feature csv files should be saved

*.saveSummaryFeatureFlag: boolean flag defining is summary csv file should be saved

*.saveFeatureList = cell array of all the features to be saved (default: all available)

*.summaryType: cell array containing the different type of operation to be executed while saving the summary file - Features can be either AVG (averaged), MEDIAN (median), STD (standard deviation), TRIMMEAN (trim mean), MAX (max value), SUM (summed)

*.saveTrimmeanParam: int value of the cutoff for trimmean (see trimmean)

*.summaryPlane: cell array defining the different plane to compute the summary on. Creates different summary for each plane. IN DEVELOPMENT

output

-

examples

```
cfg.saveSingleFeatureFlag = true;
```

```
cfg.saveSummaryFeatureFlag = true;
```

```
cfg.saveFeatureList = {'speed', 'convexhull'};
```

```
cfg.summaryType = {'AVG', 'TRIMMEAN'};
```

```
cfg.saveTrimmeanParam = 40;
```

```
emcSaveFeature(tsvFile1,tsvFile2, cfg);
```

comments

-

see also

-